



Server Configuration

Basic WebHost Manager® Setup

Change Root Password

Configure cPanel Analytics

Configure cPanel Cron Jobs

Initial Quota Setup

Server Profile

Server Time

Statistics Software Configuration

Terminal

Tweak Settings

Update Preferences

Support

Create Support Ticket

Grant cPanel Support Access

Support Center

Networking Setup

Change Hostname

Resolver Configuration

Security Center

Apache mod\_userdir Tweak

Compiler Access

Configure Security Policies

cPHulk Brute Force Protection

Host Access Control

Manage External Authentications

Manage root's SSH Keys

Manage Wheel Group Users

ModSecurity™ Configuration

ModSecurity™ Tools

ModSecurity™ Vendors

Password Strength Configuration

Security Advisor

Security Questions



## Basic WebHost Manager® Setup

&lt; All

Contact Information

Basic Config

&gt; Find

## Contact Information

Enter one or more email addresses to contact in case a problem arises with this server.

Examples: john@doe.com, john.q.public@anonymous.com, user@host.com

Enter one or more cellular phone or pager email addresses to message via email in case a problem arises with this server.

Examples: john@cellphone.com, 8005551212@provider.com, user@host.com

An API Token for the Pushbullet API

The ICQ ID that this server should use for login to ICQ when sending alerts. To disable or fine-tune ICQ notifications, go to [Contact Manager](#). You can register for a new ICQ number [here](#).

The ICQ ID password for sending alerts.

Enter one or more ICQ user identification numbers (comma delimited) you can be reached at in case a problem arises with this server.

Examples: 1234567, 11223344, 1020304

A comma-separated list of http:// or https:// URLs of a system to which you want to send POST notifications as form data with the keys "hostname", "subject", and "body". Query strings will be converted and sent as POST data. For example https://www.cpanel.net/events.cgi?apikey=XXXXX will send apikey via POST. Note that all keys and values must be in URLEncoded format. Also, if you use the https://user:password@domain.tld/ format to authenticate to the destination system, you must also URLEncode the "user" and "password" keys and values.

## Basic Config

The IPv4 address (only one address) to use to set up shared IPv4 virtual hosts.

**We strongly recommend that you only specify an IPv4 address that you have associated with this server.**

Example: 10.11.133.14

The IPv6 address (only one address) to use to set up shared IPv6 virtual hosts.

**You must enter a valid IPv6 address that you have bound to this server.**

Examples: 2001:db8::10fe:5000 or 2001:db8::

The ethernet device onto which new IP addresses are added. Devices detected with at least one IP are listed in the drop-down, or you may specify another device.

Examples: eth0:3, eth1, eth2, venet0:0 (virtuozzo servers)

Required

☒ eth0☐ Other: 

Required